

RemoteView WebViewer is a remote control technology using HTML5 that allows users to remotely connect and control devices from a web browser without the need of installing any program or module. It is available on Windows, macOS, Android and more and thanks to the High Frame Rate technology, users can enjoy a smoother, HD view without any delay of the remote device's screen.

• Use WebViewer from PC

RemoteView WebViewer Quick Guide

Use WebViewer from PC


Fast and easy WebViewer
Try it on PC in just 5 steps.

[Specifications and requirements]

	OS	Browser
Viewer (Controller side)	Windows 7 ~	Chrome 56 ~ Safari 11 ~ Edge 38 ~ Firefox 38 ~ Opera 36 ~
	macOS 10.12 ~	
Agent (Controlled side)	Windows 7 ~	
	Windows Server 2008 ~	
	macOS 10.12 ~	
	Linux CentOS x64 7.0~7.7 Linux RedHat x64 7.0~7.7 Linux Ubuntu 64x 14.04~18.04	

* The RemoteView WebViewer is available for account with 'Enterprise' license.


[Configuring and How to use RemoteView WebViewer]



STEP 1

Log in to your Enterprise account

Open RemoteView (www.rview.com) using browser from a PC, enter the [Company ID / User ID / User PW](#) and log in.




STEP 2

Enable WebViewer

After logging in, go to [[Preferences > Company settings > Connect from WebViewer](#)] and select the option [[Use All](#)] and press Apply.


- * Company settings is available on Enterprise account. For company account, please contact the administrator.
- * WebViewer does not require Simple Launcher installation to access the agent.



STEP 3

Remote access with WebViewer


Select the agent to control in "Remote PC", **right-click** on it and select [**WebViewer**] option to launch the WebViewer.



STEP 4

Remote access authentication

On the **access authentication page** opened on the browser (Chrome, Safari), enter the **Access ID/PW set** during the agent installation to remotely connect with the WebViewer.



STEP 5


Remote control with the WebViewer














Now, connect to remote PC with RemoteView WebViewer and **experience a faster and simpler remote control.**

Easy and powerful RemoteView WebViewer

It includes all the must-have key features.

Try RemoteView WebViewer.



Icon	Features	Feature description
	Mouse / keyboard control	Enables the mouse / keyboard remote control
	Function key	Available keys: Esc, Tab, Shift, Ctrl, Alt, Win
	On-screen keyboard	Run 'S/W keyboard' on the remote PC
	Send Ctrl+Alt+Del	Run Ctrl+Alt+Del
	Laser pointer	Switch mouse pointer to laser pointer
	Draw	Color: Red, Yellow, Green, Blue, Purple / Clear all
	Screen capture	Capture the current Viewer screen and save it as a file
	Aspect ratio	Select the aspect ratio displayed on the Viewer (Fit to screen, 100%, 125%, 150%)
	Full screen	Display the current Viewer in full screen (press Esc to restore to previous size)
	Screen lock	Lock and block the monitor screen of the remote PC when connected.
	Select monitor/display	Switches between the screens when the remote PC has more than 1 monitor/display.
	Quality	Set the speed as FPS (frames per second) at which data is displayed on the screen.
	Exit	Ends the remote connection.
	Hide	Hides the current Viewer's toolbar.